
Assembler Copy Code Assembler Copy Code

Assembler Copy Code

The function Generate Assembler Copy Code generates a record buffer for use in Assembler programs based on a Predict file object.

In addition, an Adabas format buffer can also be generated if required for files of the following types:

- Adabas file (file type A) with parameter Adabas SQL usage = N
- Adabas userview (file type U)



Calling the Function

The Generate Assembler Copy Code screen is displayed with function code G and object code BA in a Predict main menu or with the command GENERATE BAL or GENERATE ASSEMBLER.

```
***** PREDICT 4.2.2
09:43:39
                                                            2002-07-31
Plan
                   - Generate ASSEMBLER Copy Code -
File ID ..... CHD-A-FILE
Save as member .....
                                      Save in library .... BALLIB
Overwrite option ..... Y
                                      Op. system member ..
Punch / output .....* N
List generated code ..... Y
                            (Y,N)
                                      List offsets .....* N
Generate format buffer ....* N
                                      ADABAS version ....* I3
As DSECT ..... N
                           (Y,N)
                                      Field name prefix ..
With DC or DS .....* DC
                                      Field name suffix ..
Nr. of abstract lines .....
                            (0-16)
                                      Validate .....
Generate initial value ..... N \,
                                      Truncation .....* R
                           (Y,N)
                                      With EQUs ..... Y (Y,N)
Align .....* Y
DSECT name .....
                                      Counter length ..... 1 (1,2)
Format buffer name ......
Command ===>
Enter-PF1---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
     Help Next Stop Last LnkEl Flip Print Impl AdmFi SelFi Prof
```

Copyright Software AG 2002

Calling the Function Assembler Copy Code

Values for input fields which have been locked by your data dictionary administrator cannot be overwritten. These fields are skipped when positioning the cursor with the TAB key. See Generation Defaults.

Presettings						
The paramete	r below can be changed in the Modify BAL Defaults screen. See Generation Defaults.					
Library system	Library system for which the generated code is punched. Determines which additional cards need to be punched. An operating system member must be entered for the additional cards to be generated. See Parameters Specifying the Form of Output for more information.					
Parameters						
	rs Save as member, Save in library, Overwrite option, Op. system member, Punch/output, Workfile t generated code are described in the section Parameters Specifying the Form of Output.					
File ID	ID of the Predict file object from which the definitions are to be generated.					
List offsets	ffsets Y Include the offset of each item in the record buffer structure (relative to the beginning of the structure) in decimal and hexadecimal formats as a comment. The total length of each buffer is included.					
	P Include the absolute position (offset+1) as a comment.					
	L Include the total lengths of the record buffer and the format buffer as a comment.					
	Only allowed if parameters As DSECT=N and With DC or DS=DC. The file number and the calculated lengths of the record buffer and the format buffer are to be generated as constants in the copy code. The name of the file number constant is the record buffer name with N as prefix. The name of each length constant is the appropriate buffer name with L as prefix. Each name is prefixed, suffixed, validated and truncated in the same way as any other field name.					
	N No offset.					
Generate format buffer	Format buffer generation for Assembler copy code is only allowed if parameters As DSECT=N and With DC or DS=DC. The contents of the format buffer will correspond exactly to the contents of the record buffer. Only valid for files of type A (with parameter Adabas SQL usage set to N) or for files of type U.					
	Valid values:					
	Y Adabas format buffer is to be generated. Adabas groups, standard formats and lengths are used whenever possible. The resulting format buffers are then as short as possible.					
	F Full format buffer is to be generated. Length and format of Adabas fields are included.					
	N No format buffer is to be generated.					
	Note: If you are generating for a WANG environment, set this parameter to F or N.					

Assembler Copy Code Calling the Function

Adabas version	The version of Adabas for which the copy code is to be generated. Enter an asterisk for valid values or see table in the section Adabas Version.				
As DSECT	The effect of this parameter depends on the parameter DSECT name. See table below				
	As DSECT	DSECT name	Copy Code Generated		
	Y	specified	<dsect name=""> DSECT</dsect>		
	Y	blank	<file-id> DSECT</file-id>		
	N	specified	<dsect name=""> DS OCLnnn</dsect>		
		specified	Note.: nnn=Length of the record buffer structure		
	N	blank	Only entries for fields are generated		
	N	* (agtarials)	<file-id> DS OCLnnn</file-id>		
		* (asterisk)	Note.: nnn=Length of the record buffer structure		
Field name prefix	The prefix to be used for each field name generated.				
With DC or DS	DC Assembler DC (define constant) instruction is to be used. If AS DSECT=Y, this parameter must be set to DS.				
	DS Assembler DS (define storage) instruction is to be used.				
Field name suffix	The suffix to be used for each field name generated.				
Nr. of abstract lines	The number of Predict abstract lines per field to be included in the generated code.				
Validate	Determines how invalid characters are handled.				
	blank Invalid characters in a field name will result in an error message but will not be mod				
	rep.char Invalid characters in a field name are replaced by this character. Valid replace characters: letters A-Z, digits 0-9, \$, \$ and #.				
	* Invalid characters in a field name are deleted.				
Generate	This option takes effect only when With DC or DS=DC and As DSECT is set to N.				
initial value	N No initialization.				
	Statements are generated to initialize the structure with the value specified for Init value in the corresponding field object in Predict. Fields with no value for Init value are initialized with zeros or blanks. Aligned 8-digit fields with format B or I are not initialized. In a PE group with the 3GL specification Gr.structur set to blank, only the first occurrence of each field is initialized.				

Copyright Software AG 2002 3

Truncation	ion Specifies which characters are deleted if a generated field name is too long:					
	L truncate from the left					
	R truncate from the right					
	M truncate from the middle					
	A warning is given if field names are truncated.					
Align	Determines which fields are to be aligned. Fields are aligned on the boundary shown in the table in the section Field Format and Assembler Copy Code.					
	Y All appropriate fields are aligned.					
	N No fields are aligned.					
	S Fields are aligned only if the corresponding Predict field object has the 3GL specification Synchronized=S.					
With EQUs	Y EQU statements are to be generated for fields of length 1 whose format is not P and comment lines are to be generated for other fields, using any condition names defined as attributes of the Predict field objects. These names are prefixed, suffixed, validated and truncated in the same way as field names. For fields of format L where no condition name was specified, a condition name is generated by concatenating the field name "Example" to the prefix N. In this case the following statement is generated: NEXAMPLE EQU X'00'.					
DSECT name	Specifies the name of the record buffer in the generated structure. The effect of this parameter depends on parameter AS DSECT. See above in this table.					
Counter length	Length of additional counter fields. Valid values: 1, 2					
Format buffer name	Specifies the name of the format buffer in the generated structure. If omitted, the file ID prefixed by F is used.					

Names in Assembler Copy Code

The following rules apply to the generation of names for Assembler copy code.

- Alpha characters in Predict object IDs, such as file and field IDs, are converted to upper-case.
- Each field name (label) used in Assembler copy code is taken from the corresponding Predict field object: either the field name synonym for Assembler or, if none exists, the Predict field ID.
- All field names and any condition names are prefixed, suffixed, validated and if necessary truncated to 8 characters according to the parameter settings.
 - For example, with Field name prefix set to JUN, Field name suffix to *86, Validate to § and Truncation to R two fields JUNCDAY§ and JUNDAY§8 are generated for a field of type MC called DAY.
- If a resulting field name is not unique within the entire file structure, an error message is given.
- Any DSECT name or format buffer name does not receive the field name prefix and suffix. The value supplied

may not contain invalid characters.

• If the file ID is taken as default DSECT name or, with the prefix F, as default format buffer name, it is validated and if necessary truncated.

Assembler Names for Counter Fields - MC or PC

Before each field of type MC or PC, a counter field is generated automatically in the copy code, with a name created from the name of the MC or PC field prefixed by C.

For example, a Predict field object DAY with no field name synonym for Assembler and with type MC will generate two fields with the names CDAY and DAY.

Assembler Names for Logical Fields - L

If no condition name is defined for a logical field (format L), the field name prefixed by N is used for the EQU statement.

Assembler Names for Fields of Type AV

For fields of format AV, a group is generated where groupname=fieldname. The group contains a length field and a text field prefixed with L and T respectively. See second table in the section Field Format and Assembler Copy Code.

Assembler Names for Additionally Generated Indicator Fields

An additional indicator field prefixed with S is generated in the following cases:

- a field is defined with Suppression option set to U (null allowed)
- a field of a file of type A, U or B is defined with Suppression option set to R (not null)

Note

For Adabas Fields, the additional indicator field is only generated for the following Adabas versions:

- I3 or above
- U1 or above
- V4 or above.

Field Format and Assembler Copy Code

Fields in the Assembler copy code have a clause determined by the following factors:

- length and format of the corresponding Predict field object
- file type of the file containing the field

Copyright Software AG 2002 5

Predict Format	File Type	PRD Length	Alignment Boundary	Assembler Clause	(if aligned)	Note
В		1		XL1		
		l=3,5,6,7		XLl		
I		1		XL1		
B/I		2	2	XL2	Н	
		4	4	XL4	FL4	
		8	4	XL8	FL8	
В		<i>l</i> =>9		PIC X(l)		
F		4	4	CL4	Е	
		8	8	CL8	D	
N/U NS/US (nn+m<17)		nn.m		ZLl		l=nn+m
N/U NS/US (nn+m>16)		nn.m		CL1		l=nn+m
P/PS		nn.m		PLl		l=(nn+m+2) /2
D	D, E			CL10		
	other			PL4		
Т	D, E			CL8		
	other			PL7		
L				XL1		
G		n		CLm		m=2*n
GL		n		CLm		m=2*n
GV		n		CLm		m=2*n
LO	D, E		4	XL4	FL4	

The clause XLn is normally generated for B formats. There are two exceptions to this rule:

- parameter Align is set to Y, or
- parameter Align is set to S and the field is defined in Predict as Synchronized.

The clause H or FL4 or FL8 is normally generated for I formats. The exception to this rule is when the parameter Align is set to N and the field does not start at a "synchronized" address.

An indicator or length field is generated like a B2 field. A counter field is also generated like a B2 field if Counter length = 2. If Counter length = 1, the clause XL1 is generated.

A numerical format field with a length \geq 17 is treated in Assembler copy code as alphanumeric format field. No INIT VALUE can be generated for these fields and a warning is given.

Assembler Copy Code Sample Output

A DB2 large object is generated as locator like an I4 field.

Note:

When generating Assembler copy code for DB2 tables and views, format NS or US is converted to Assembler format PL. Any redefinitions that exist for this field are skipped.

File Type in Predict	Predict Format	Length	Assembler Clause	Note
D, E	A, AL	n	CLn	
	AV	Two-level group is generated: Fieldname DS CLm FieldnameL Dx yyy FieldnameT Dx CLn		m = n + 2 Dx is either DS or DC, depending on parameter With DC or DS. yyy is either XL2 or H, like a B2 field.
A,U,B	A	n	CLn	
	AV	Two-level group is generated. See above.		

Sample Output

```
13:27:40
                  ***** PREDICT 4.2.2 *****
                                                          2002-07-31
                  - Generate ASSEMBLER Copy Code -
                                                          Page: 1
File ID .. GENERATION-EXAMPLE
    THIS RECORD-BUFFER LAYOUT WAS GENERATED BY PREDICT
        FOR FILE: GENERATION-EXAMPLE
            ON: 2002-07-31 STARTING AT 13:27:40
   FILE COMMENTS: Example file for the
                 PREDICT generation subsystem
******************
GROUP1 DS 0CL99
ELN9V5 DC ZL14'0'
                        ELE-N-9V5
GRINGR DS 0CL30
ELEB4 DC FL4'0'
                        ELE-B-4
                  CONDITION NAMES:
                  INIT-ELE-B-4=00001000
                  COND-ELE-B-4-V-1=FFFFFFFF
ELPS52 DC PL4'0'
                        ELE-PS-5V2
            5FL4′0′
MUB4
       DC
                        MU-B-4
       ORG MUB4
MURB7
       DC
            XL7′0′
                        MU-RED-B-7
MURB13
       DC
            ZL13'0'
                        MU-RED-US-13
       ORG MUB4
MURB8
            XL8'0'
                        MU-RED-B-8
                 CONDITION NAMES:
                 MU-RED-B-8-COND1=111111
```

Copyright Software AG 2002

Sample Output Assembler Copy Code

```
***** P R E D I C T 4.2.2 *****
                                                            2002-07-31
13:27:40
                  - Generate ASSEMBLER Copy Code -
                                                            Page: 2
            CL12
       DS
            CL42''
ELEA42
      DC
                         ELE-A-42
                   CONDITION NAMES:
                   COND-NAME-START=COND-START
                   *THRU=COND-ZEND
ELEF8 DC D'0'
                         ELE-F-8
ELEB3 DC XL3'0'
                         ELE-B-3
CPCOCC7 DC XL1'0'
                         CNT OF PC-OCC-7
PCOCC7 DS 0CL76
PCNS7V3 DC ZL10'0'
                        PC-ELE-DE-NS-7V3
CPCMCPS DC XL1'0'
                         CNT OF PC-MC-PS-6V1
PCMCPS DC 11PL4'0'
                         PC-MC-PS-6V1
PCGR DS
            0CL17
BALI2
       DC
            H'0'
                         PC-ELE-I-2
PCPS20V7 DC
            PL14'0'
                         PC-PS-20V7
BALF4
       DC
            E'0'
                         PC-ELE-F-4
       DS
            6CL76
            PL4′0′
ELED
       DC
                         ELE-D
            PL7′0′
      DC
ELET
                         ELE-T
      DC
            XL1'0'
                         ELE-L
ELEL
NELEL EOU X'00'
*******************
    THIS FORMAT-BUFFER WAS GENERATED BY PREDICT
       FOR FILE: GENERATION-EXAMPLE
             ON: 2002-07-31 STARTING AT 13:27:40
********************
FGENERAT DS 0CL295
* >>> DIC1809 WARNING: FIELDNAME(S) TRUNCATED
            CL50'AB, 2X, AD, AE, AF1-5, AG, 2X, AH, AI, ALC, AM1, AN1C, 2, AN1(1'
       DC
             CL50'-11), 1X, AP1, AQ1, AR1, AM2, AN2C, 2, AN2(1-11), 1X, AP2, AQ'
       DC
            CL50'2, AR2, AM3, AN3C, 2, AN3(1-11), 1X, AP3, AQ3, AR3, AM4, AN4C'
       DC
           CL50',2,AN4(1-11),1X,AP4,AQ4,AR4,AM5,AN5C,2,AN5(1-11),1'
       DC
           CL50'X,AP5,AQ5,AR5,AM6,AN6C,2,AN6(1-11),1X,AP6,AQ6,AR6,'
       DC
            CL45'AM7, AN7C, 2, AN7(1-11), 1X, AP7, AQ7, AR7, AS, AT, AU.'
*******************
DIC1800 SUMMARY: 25 FIELD(S) PROCESSED
DIC1809 WARNING:
                 1 FIELDNAME(S) TRUNCATED
DIC1819 MESSAGE: 11 SLACK BYTE(S) GENERATED
DIC1847 MESSAGE:
                3 FIELD(S) SKIPPED FOR RECORDBUFFER STRUCTURE
```

Copyright Software AG 2002

8